

Software Code: SC000000000464	Product family: MODUS3 X
Last available release: 1.30	

Firmware changelog

REL.	DATE	RELEASE NOTES
1.30	05/06/2025	New features and improvements: <ul style="list-style-type: none"> Added complete codepage 858 for every font dimension table Bug fixes: <ul style="list-style-type: none"> Fixed issue with Jam status not released using MODUS3 X model with "B" papermouth
1.23	25/Sep/2024	Bug fixes: <ul style="list-style-type: none"> Removed compression in RS232 when printing graphical data
1.19	13/Dec/23	New features and improvements: <ul style="list-style-type: none"> Added anti-jam feature Improved logos management: max logo dimension is now 640x408 dots Added Setup parameter for paper saving: "Line space reduction", "Line feed reduction", "Barcode height reduction" Max loop length in Loopaway mode: 35 cm Added user-defined character size 24x24 for Chinese fonts (command 0x1B 0x26) Improved feedaway/loopaway management Improved jam management Improved alignment management Added status flag for anti-jam sensor and ejector motor ON (see command 0x10 0x04 0x14) Bug fixes: <ul style="list-style-type: none"> Fixed Setup parameter "Paper filter width" Fixed Setup parameter "Notch min width"
1.09	07/Jul/23	New features and improvements: <ul style="list-style-type: none"> Expanded selection for Output Mouth parameter. From "Enabled" to "Type A" or "Type B"

1.08	12/Jun/23	<p>Bug fixes:</p> <ul style="list-style-type: none"> • Improved paper jam management • Added paper jam report in status also for "Jam out" error • Parameters for minimum ticket length command 1D E8 nH nL: the order is now compliant with the commands documentation • Fixed bug in command "Print Raster Bit" 1D 76 30 <p>New features and improvements:</p> <ul style="list-style-type: none"> • For printers without presenter, "Output Mouth" value is disabled by default
1.00	31/Jan/23	First firmware release